


Intelligibility

Overview


The Intelligibility meter uses inter **plug-in** communication to receive audio data from **Relay** **plug-in** instances to allow for the monitoring of dialogue intelligibility in the context of different **listener** environments.



Configuration

The following steps outline the setup and recommended configuration for the Intelligibility meter:

1. Insert **Insight 2** on the master bus.
2. Insert **Relay** on a dialogue bus or track.
 - > **Relay** should be inserted on the bus or track that is feeding into the master bus. e.g. if multiple tracks are being sent to a dialogue submix which is then routed to the master bus, insert **Relay** on the dialogue submix rather than the individual dialogue track.
 - > If other **plug-ins** are inserted on the dialogue bus, add **Relay** to the *last* available insert slot.
 - > For the best results, ensure that **Insight 2** and **Relay** are inserted on tracks that use the same channel configuration. e.g. **Insight 2** is inserted on a 5.1 master bus, **Relay** is inserted on a 5.1 submix bus.
3. In the Intelligibility meter panel, select the **Relay** instance on the dialogue bus in the source list. Click "OK" to dismiss the source list view.



Meters and Controls

The following meters and controls are available in the Intelligibility meter panel.


Intelligibility Meter

The top meter bar is the Intelligibility meter. This meter displays estimated intelligibility (dot meter) of the selected source, the recommended range of intelligibility for the selected **Listener Environment**, and a history meter that displays the range of the estimated intelligibility values over the course of 10 seconds.



Listener Environment

The menu above the intelligibility meter selects between different noise levels in a listener's environment and recommends an intelligibility range for the source instance.




Choices include:

- > Low Noise
- > Medium Noise
- > High Noise


Recommended Range

The green range display in the intelligibility meter updates to reflect the suggested range of dialogue intelligibility when listening to the full mix in low, medium, or high noise environments.


Low Noise:



Medium Noise:



High Noise:



Estimated Intelligibility

The dot meter represents the estimated intelligibility of the selected source instance.



Source Meter

The source meter displays the perceived loudness (phons) level of the selected source plug-in. The thin meter above the main meter bar is a history meter that displays the range of the source meter values over the course of 10 seconds.



Difference Meter


The difference meter displays the estimated difference between the perceived loudness levels of the output (Insight 2) and the selected source instance. The thin meter above the main meter bar is a history meter that displays the range of difference meter values over the course of 10 seconds.



Levels

Overview

The **Level** meter panel displays both instantaneous (true-peak) and averaged (RMS) levels for each channel of input audio. **Insight 2** expands on the surround support of **Insight 1**, adding for support for monitoring levels of tracks with up to 10 channels, including support for up to Dolby Atmos 7.1.2 channel configurations.



Options

The following options are available for the **Levels** meter panel:

Meter Specific Options

Meter Specific Options

Loudness

Levels

Sound Field

History

Spectrum

Spectrogram

Meter display type

Peak + RMS

Scale

dB (non-linear)

☒ Show Peak Hold

Peak hold time (ms)

1000

Integration time (ms)

300 (VU)

Readout Type

Max Peak

Surround display format

SMPTE

Color

Grayscale

?

Reset

Cancel

Ok

METER DISPLAY TYPE

Sets the type of metering used for by the True Peak meters. Available options include Peak + RMS and K-System.

SCALE

For Peak + RMS, selects between dB (linear) and dB (non-linear). For K-System metering, selects between K-12, K-14, and K-20.

SHOW PEAK HOLD

Determines if the peak hold display will be shown in the level meters.

PEAK HOLD TIME

Cycles through different peak hold times. The choices include: 5ms, 250ms, 500ms, 1000ms, 5000ms, and infinite. If set to infinite, the peak value will be held until you double click on the meter.

INTEGRATION TIME

Only applies if the level meter displays RMS. It lets you specify the integration time for the RMS calculation. In most RMS meters, the integration time is set to around 300ms.

READOUT TYPE

Determines the type of text readout displayed above the peak indicators.

SURROUND DISPLAY FORMAT

Determines the display order of surround level meters. Choices include: SMPTE and Film.

COLOR

Selects the color preset for the level meter displays.

Loudness

Overview

The Loudness panel includes measurements used to ensure loudness compliance when delivering media for broadcast TV or streaming services. Loudness measurements are based on the ITU-R BS.1770 recommendation¹, which defines audio measurement algorithms for determining true peak signal level and subjective loudness over the course of a program.

The Loudness meter panel features dynamic [view configurations](#) based on the height of the meter panel, [loudness measurements](#), common [loudness standard target presets](#), and a [Targets control panel](#) for customizing meter targets and the loudness measurement [Gate](#) mode.




Views

There are two possible views available in the Loudness meter panel: [minimized](#) and [maximized](#). These views are shown dynamically based on the *height* of the Loudness meter panel.

Minimized view

The minimized view configuration is dynamically loaded when the *height* of the Loudness meter panel is *less than 270 pixels*. The meter bars are hidden in minimized view to provide a compact overview of loudness statistics.



Maximized view

The maximized view configuration is dynamically loaded when the *height* of the Loudness meter panel is *equal to or greater than 270 pixels*. The meter bars are displayed alongside the text readouts in maximized view configuration to provide a full overview of loudness statistics.




Measurements

The following image outlines the measurements available in the Loudness meter panel:



Momentary

Measures loudness over the course of 400 milliseconds. Momentary loudness measurements are **never gated**, regardless of the currently selected **Gate** option in the **Targets control panel**.




MOMENTARY MEASUREMENT IN MINIMIZED VIEW

When the **minimized view** configuration is active, all loudness meter bars are hidden from view. Increase the height of the Loudness meter panel to access **maximized view** or utilize the Momentary loudness trace in the **History** meter panel to monitor Momentary loudness activity.


Momentary Maximum

Displays the **maximum Momentary** loudness value measured over the duration of the loudness calculation. Momentary loudness measurements are never gated, regardless of the currently selected **Gate** option in the **Targets control panel**.



Loudness Range (LRA)

Measures the loudness range of the source material over the course of the entire loudness calculation. Loudness Range is measured in LU (Loudness Units), where 1 LU is equal to 1 dB. When the **Dialogue Gate** option is selected in the **Targets control panel**, a "(DIA)" label will be displayed next to the LRA measurement label.



LRA TARGET RANGE

LRA Target Range values can be customized in the **Targets control panel**. Selecting a **Loudness Standard Target Preset** will set the LRA target range to the values associated with the selected loudness standard.

Loudness Range (LRA) Meter Bar

Displays the loudness range of the source material as a white vertical bar along the left edge of the **Integrated** meter bar.



True Peak Maximum

Displays the maximum true peak level measured across all channels for the duration of the loudness calculation.




PEAK TARGET CONTROL

The **Peak target** value can be customized in the **Targets control panel**. Selecting a **Loudness Standard Target Preset** will set the **Peak target** to the value associated with the selected loudness standard.

Loudness Standards and Targets

The bottom of the Loudness meter panel includes a list of **Loudness Standard Target Presets** and a **Targets control panel** with options for customizing meter target values and loudness gating options.




TARGET SAVING BEHAVIOR

Any **customized** or **preset** loudness target configurations:

- > **Will not save** with **Layout** presets.
- > **Will not** be affected when the **Layout** preset selection changes.
- > **Will** save with sessions.

Loudness Standard Target Presets

This dropdown menu includes a number of common loudness standard target presets (detailed in the **table below**).



The following meter targets and controls are affected when a loudness target preset is loaded: **Loudness target**, **Peak target**, **LRA target range**, and **Gate**.

Insight 2.1 Loudness Standard Target Presets

Preset Name	Integrated	Tolerance	Gate	True Peak	Notes
AES AG0TTVS TD1006.1.17-10 ²	-16 LUFS	± 2.0 LU	On (Program)	-1 dBTP	
AGCOM 219/09/CSP	-24 LUFS	± 0.5 LU	On (Program)	-2 dBTP	Italy
ARIB TR-B32 A/85	-24 LKFS	± 2.0 LU	On (Program)	-1 dBTP	Japan
ATSC A/85	-24 LKFS	± 2.0 LU	On (Program)	-2 dBTP	USA, Canada, Puerto Rico
BS.1770-1 ¹	-24 LKFS	± 2.0 LU	Off	-2 dBTP	International
BS.1770-2/3/4 ³	-24 LKFS	± 2.0 LU	On (Program)	-2 dBTP	International

Preset Name	Integrated	Tolerance	Gate	True Peak	Notes
EBU R128 ⁴	-23 LUFS	± 0.5 LU	On (Program)	-1 dBTP	Europe
EBU R128 DPP	-23 LUFS	± 0.5 LU	On (Program)	-3 dBTP	Europe
EBU R128 (South Africa)	-23 LUFS	±1.0 LU	On (Program)	-2 dBTP	South Africa
OP-59	-24 LKFS	±1.0 LU	On (Program)	-2 dBTP	Australia/New Zealand
Portaria 354	-23 LUFS	± 0.5 LU	On (Program)	-2 dBTP	Brazil
Netflix ⁵	-27 LKFS	± 0.5 LU	On (Dialogue)	-2 dBTP	> Dialogue Target LRA of 7 LU or less > Based on v1.0 of Netflix Audio Mix Specifications and Best Practices ⁵

Targets Control Panel

The **Targets control panel** allows for the customization of meter target values and the type of **Gate** used when measuring integrated loudness. Adjusting the meter targets will determine when the associated meter will change color to indicate that it has exceeded the target value.


The **Targets control panel** can be accessed by clicking on the button to the left of the loudness standard target preset dropdown menu. The panel will be pinned open and can be dismissed by clicking on the button again.



CUSTOM TARGETS

When any parameter in the **Targets control panel** is modified, the target preset name will be updated to **"Custom"** to indicate that the values have been modified.

The following image outlines the parameters available in the **Targets control panel**:




TIP: ADJUSTING LOUDNESS AND PEAK TARGET VALUES

The following methods can be used to modify the **Peak** and **Loudness** target values in the **Targets control panel**:

- > **Click and drag** the mouse up or down to modify the target value.
- > **Enter target values manually**: Double-click on the desired target value readout, Type the new value into the text edit field, Press the return key or click anywhere in the interface to dismiss the edit field.

Loudness Target

Sets the **loudness target** value for the **Integrated**, **Short-term**, and **Momentary** loudness meters.



When the **Integrated** measurement has **exceeded** the loudness target, **Integrated** measurements will be displayed in **red**. When the **Momentary**, **Momentary maximum** or **Short-term** measurements have **exceeded** the loudness target, the associated meters and readouts will be displayed in **yellow**.



HISTORY METER: LOUDNESS TARGET


When the **loudness target** is adjusted, the red dotted line in the **History** meter will update to reflect the new loudness target value.

Peak Target

Sets the true peak target value in the **Loudness** and **Levels** meter panels.



When the maximum True Peak level (across all channels) is **below** the **Peak target** value, the readout will be displayed in **white** text. When the maximum True Peak level (across all channels) **exceeds** the **Peak target** value, the readout will be displayed in **red** text.



PEAK TARGET IN LEVELS METER PANEL

When the **peak target** is adjusted to a negative value, a red dotted line will be drawn in the **Peak+RMS** meter bar displays in the **Levels** meter panel to indicate the adjusted **peak target** value.

LRA Targets

Sets the upper and lower target values for the **Loudness Range (LRA)** text readout. LRA targets can be set to values within a range of 0 LU and 30 LU.



Any LRA measurement that falls **between the two target values** will be considered as **in range** and the readout will be displayed in **white** text. Any LRA value that falls **outside of the LRA target range** will be displayed in **red** text.


Within target range	Outside of target range
LRA 6.0 LU	LRA 0.8 LU

TIP: ADJUSTING LRA TARGETS

- Click and drag the slider handles left or right.
- Arrow Key Adjustments:
 - Left Arrow Key: Shifts the target range down by reducing both of the target values by 1 LU per key press.
 - Right Arrow Key: Shifts the target range up by increasing both of the target values by 1 LU per key press.
 - Up Arrow Key: Increases the LRA target range by subtracting 1 LU from the minimum value and adding 1 LU to the maximum value with each key press.
 - Down Arrow Key: Decreases the LRA target range by adding 1 LU to the minimum value and subtracting 1 LU from the maximum value with each key press.

Gate

There are three different gating options for loudness calculations in the Loudness meter panel: **Off**, **Dialogue**, and **Program**. Gating is employed in loudness measurements in order to exclude quieter sections of a program from lowering the overall loudness measurement (**Program-gated**) or to measure the loudness of a program using dialogue as an anchor element (focal point) for the loudness calculation (**Dialogue-gated**).



Off

When **Off** is selected, no gating method is enabled when calculating loudness. When selected, the loudness measurements are based on the BS.1770-1¹ recommendation, which did not employ the -10 LU relative **program** gate.

Dialogue

Enables a loudness gating method that detects if dialogue is present in the source material. Only segments of the program where dialogue is detected will contribute to the **Integrated** loudness measurement. When selected, the loudness measurement is based on the ITU-R BS.1770-1 revision². The -10 LU relative **program** gate threshold is **not** when the dialogue gate is enabled.

▲ DIALOGUE-GATED LOUDNESS: INITIAL DRAWING DELAY

- The algorithm used to calculate dialogue-gated loudness requires at least two seconds of incoming audio in order to begin detecting dialogue content in the input signal.
- This two second delay can be observed in the initial drawing of the following measurements:
 - Dialogue-gated **Integrated** measurements in the Loudness meter panel.
 - The **Short-term**, **Momentary**, and **Integrated** loudness traces in the **History** meter panel.
- This delay does not affect the accuracy of the loudness measurements.

Program

Enables a -10 LU relative gating threshold when calculating loudness in order to exclude lower level noise from decreasing the overall loudness measurement of a program. The BS.1770-2/3/4 revisions of the ITU-R BS.1770 recommendation³ requires that a -10 LU relative program gate threshold is applied when calculating integrated loudness.

Calculation Settings


Controls for resetting, pausing or holding loudness meter calculations are located in the header of the Insight plug-in window.




■	Reset	Manually resets all loudness calculations in the Loudness and History meters.
■	Pause	Freezes all meters in the Loudness , History , and Spectrogram meter panels. All values in applicable meters (Loudness , History , and Spectrogram) are retained when Pause is enabled, regardless of the transport state of the DAW/NLE.
■	Hold	When enabled , the current loudness values will be retained when the transport is stopped. The calculation will continue from the last known value when the transport is started again. When disabled , the Loudness meter calculations will reset each time the transport is started.

Options

To access **Loudness meter options**, click on the **gear** button in the upper left-hand corner of the **Loudness meter panel** to open the **Meter Specific Options** window.



The **Loudness** tab of the **Meter Specific Options** window includes options for modifying the **scale** and **range** of measurements displayed in the **Loudness meter panel**.



■ METER SPECIFIC OPTIONS SAVING BEHAVIOR

- Meter Specific Options are **saved with Layout presets**.
- Meter Specific Options are **saved with sessions**.

Range

Determines the minimum/maximum loudness values displayed in the **Loudness meter scales**. Available Range options include: **dB (linear)**, **dB (non-linear)**, **BS1771 EBU +9**, and **EBU +18**.

dB (linear)

Full scale (dBFS) range for measuring loudness. The scale values are evenly spaced in this mode, **ranging from -inf dBFS to 0 dBFS**.

dB (non-linear)

Full scale (dBFS) range for measuring loudness. The scale values are logarithmically spaced in this mode, **ranging from -inf dBFS to 0 dBFS**.

BS1771

Loudness meter scale range recommended by the ITU⁴. The scale mark values displayed differ depending on the **Scale** type selection (e.g. **Absolute** or **Relative**):

- Absolute** range: **-45 LUFS to -14 LUFS**
- Relative** range: **-21 LU to +9 LU**

EBU +9

Loudness meter scale range recommended by the EBU as a default setting. The scale mark values will differ depending on the **Scale** type selection (e.g. **Absolute** or **Relative** scale).

- > **Absolute** range: **-41 LUFS to -14 LUFS**
- > **Relative** range: **-18 LU to +9 LU**

EBU +18

Loudness meter scale range recommended by the EBU for material with a wide loudness range. The scale mark values will differ depending on the **Scale** type selection (e.g. **Absolute** or **Relative** scale).

- > **Absolute Scale** Range: **-59 LUFS to -5 LUFS**
- > **Relative Scale** Range: **-36 LU to +18 LU**

Scale

Determines the scale and units used in the loudness meter bar displays. Available scale options include: **Absolute** or **Relative**.


Absolute

Displays loudness values in LUFS (Loudness Units, relative to Full Scale).



Relative

Displays loudness values in LU (Loudness Units) that are relative to the current **Loudness Target** value.



RELATIVE SCALE EXAMPLE

If the **loudness target** value is set to -23, a value of 0 LU in **Relative scale** mode is equivalent to -23 LUFS in **Absolute scale** mode.

Related Meters


- > **History meter panel**: Monitor loudness values over time with the History meter.
- > **Levels meter panel**: View Peak+RMS or K-System metering information for each channel.

1. [Rec. ITU-R BS.1770-1 \(09/2007\)](#)
[\[return\]](#)
2. [Technical Document - AES1006.1-17-10: Loudness Guidelines for OTT and OVD Content - October 2017](#)
[\[return\]](#)
3. [Rec. ITU-R BS.1770-4 \(10/2015\)](#)
[\[return\]](#)
4. [EBU Recommendation: R 128 Loudness normalisation and permitted maximum level of audio signals](#)
[\[return\]](#)
5. [Netflix Audio Mix Specifications and Best Practices \(v1.0\)](#)
[\[return\]](#)
6. [Rec. ITU-R BS.1771-1 \(12/2012\): Requirements for loudness and true-peak indicating meters](#)
[\[return\]](#)

History

Overview

The History meter panel draws traces over time for the following loudness measurements: **Integrated**, **Short-term**, and **Momentary**. To learn more about the different loudness measurements, see the **Loudness** chapter.



Resizing

The History meter can be resized using the following methods:

- › Clicking and dragging the bottom right corner of the main **Insight** plug-in window up or down.
- › Clicking and dragging the dividers between meter panels.
- › Clicking the maximize/minimize toggle button in the upper right hand corner of the History meter panel.

Displays and Rulers

Cursor Position Readout

When hovering the cursor over the history graph, a text readout will appear with information about the measurements at that point in time. Current time; M = Momentary; S = Short-term; I = Integrated.



Integrated Loudness Target Line

The **Integrated** loudness target set in the **Loudness** meter panel is indicated by the horizontal dotted red line displayed in the loudness history graph.



When the Integrated loudness trace has exceeded the **Integrated** target, the trace will be drawn in red.



INTEGRATED LOUDNESS TRACE & GATE

The **Gate** selection in the **Loudness** meter panel influences the values used to draw the Integrated loudness trace. See the **Loudness** chapter for more information about the Gate options.

▲ DIALOGUE-GATED LOUDNESS: INITIAL DRAWING DELAY


- › The algorithm used to calculate dialogue-gated loudness requires at least two seconds of incoming audio in order to begin detecting dialogue content in the input signal.
- › This two second delay can be observed in the initial drawing of the following measurements:
 - › Dialogue-gated **Integrated** measurements in the **Loudness** meter panel.
 - › The **Short-term**, **Momentary**, and **Integrated** loudness traces in the **History** meter panel.
- › This delay does not affect the accuracy of the loudness measurements.
- › For more information about dialogue-gated loudness measurements, see the **Loudness** meter chapter.

Zooming

- › Zoom on the time scale or loudness scale by hovering the cursor over the axis and using the mousewheel or trackpad to zoom in or out.
- › Click and drag on the time or loudness scales when zoomed in to modify the view range.
- › Double-click on the time or loudness scales to reset the zoom level to default.

Options

The History meter options menu can be accessed by clicking the gear button in the upper left-hand corner of the History meter panel. The History options tab allows for individual loudness trace visibility to be toggled on or off.



Enable or disable the history trace displays using the following options:

- › **Display integrated loudness trace:** Shows/hides the integrated loudness history trace.
- › **Display short-term loudness trace:** Shows/hides the short-term loudness history trace.
- › **Display momentary loudness trace:** Shows/hides the momentary loudness history trace.

GLOBAL OPTIONS: LOUDNESS HISTORY CSV EXPORT

- › The **Global Options** window includes an option to export a .csv file of loudness history values.
- › To access the **Global Options** window, click on the **gear** button in the upper right-hand corner of the **Insight 2** plug-in window.
- › Learn more about the **Loudness** related options in the **Global Options** chapter.

Related Meters

> **Loudness:** Monitor program loudness and adjust loudness target values to ensure loudness compliance.

Spectrogram

Overview

The Spectrogram provides an intuitive way to pinpoint individual elements within a mix. The Spectrogram can display data for up to 8 sources simultaneously for analysis by selecting **Relay** instances in the source selection menu.


What is a spectrogram?

A Spectrogram is a spectral representation of audio varying over time. The vertical axis represents frequency while the horizontal axis represents time. Amplitude is displayed as color intensity in the 2D Spectrogram and as height in the 3D Spectrogram.


Views

The spectrogram offers two view modes: 2D and 3D.

2D Mode:



3D Mode:



Preset 3D Camera Views

The buttons along the bottom of the spectrogram meter panel (when 3D mode is selected) allow for quick adjustment of 3D spectrogram camera angles.



Single- or double-clicking and dragging on the spectrogram display will rotate the view angles

Options

Spectrogram specific options can be accessed by clicking the gear button in the upper left hand corner of the spectrogram panel.

Perspective 3D	3D options	2D options
Color Grayscale	Zoom 3.3	Scroll speed Slow
FFT overlap 75%	Height 0.333	
FFT size 4096	History length 26.2	
	Level of detail High	

The following options are available for the Spectrogram meter panel:

General



PERSPECTIVE

Selects 2D or 3D spectrogram view.

COLOR

Selects the color scheme for the spectrogram.

FFT OVERLAP

Adjusts how often the spectrum is computed. Higher values compute the spectrum more often.

FFT SIZE

Adjusts the frequency and time resolution used to draw the spectrogram.

3D Options



The following options apply to the 3D spectrogram only:

ZOOM

Zooms in and out on the center of the 3D spectrogram.

HEIGHT

Scales the amplitude (z-axis) of the 3D spectrogram.


HISTORY LENGTH

Scales the time (y-axis) of the 3D spectrogram.

LEVEL OF DETAIL

Adjusts the level of detail used when drawing the 3D spectrogram. Low detail may improve performance.

2D Options




The following option applies to the 2D spectrogram only:

SCROLL SPEED

Adjusts the time scale length of the 2D spectrogram.

Inter Plug-in Communication

Up to 8 sources can be displayed at a time in the Spectrogram. To access the source selection display, click the dropdown menu to the right of the gear button in the meter panel.




The source panel lists all available **Relay** plug-in instances in the session.
To display an instance in the spectrogram, check the box to the left of the instance name.
To change the color of a specific instance, click on the color box on the right side of the list. Select the desired color in the color selection window and click Ok to save changes.

🚩 Spectrum

Overview

A Spectrum Analyzer is a meter that measures amplitude across the frequencies which encompass the spectrum of human hearing. The vertical axis represents amplitude while the horizontal axis represents frequency.



Cursor Position Readout

Hovering a cursor anywhere in the spectrum analyzer will display a readout of the frequency and amplitude at that location.

Zooming and Scrolling

Both the frequency and decibel scales are freely zoomable and draggable. To zoom in on a given scale simply hover over the scale and use your mouse wheel to zoom in or out. To drag a given scale simply click anywhere on the scale and drag it in the desired direction. Double-click on either scale to return to the default view.

Options

The Spectrum Analyzer includes the following options:



- > **SPECTRUM TYPE:** Selects between 4 different types of spectrums.
 - > **LINEAR:** a continuous line connecting the calculated points of the spectrum.
 - > **1/3 OCTAVE:** Splits the spectrum into bars with a width of 1/3 of an octave. Although the spectrum is split into discrete bands, this option can provide excellent resolution at lower frequencies.
 - > **FULL OCTAVE:** Splits the spectrum into bars with a width of one full octave.
 - > **CRITICAL BANDS:** Splits the spectrum into bands that correspond to how we hear, or more specifically how we differentiate between sounds of different frequencies. Each band represents sounds that are considered "similar" in frequency.
- > **AVERAGE TIME:** Spectrum is averaged according to this setting. Higher average times can be useful for viewing the overall tonal balance of a mix, while shorter average times provide a more "real time" display.
- > **PEAK HOLD TIME:** Selects between specific hold times in milliseconds, or Infinite, where the peak is held indefinitely.
- > **WINDOW SIZE:** Controls the trade off between frequency and time resolution in the spectrum. Higher values will let you see smaller peaks in the spectrum, but the spectrum will update more slowly.
- > **WINDOW:** Selects a window type for the spectrum. In most cases the default window type will work well, but you can choose from a variety of window types. Each window type has different amplitude and frequency resolution characteristics.
- > **OVERLAP:** Controls how often the spectrum updates. More overlap will cause the spectrum to update more frequently, at the expense of increased CPU usage.
- > **SHOW PEAK HOLD:** Turns the peak hold display on/off.

Sound Field

Overview

The Sound Field meter panel features a stereo vectorscope and a surround scope meter.

Vectorscope

A Vectorscope is a meter that juxtaposes the two channels of a stereo signal on an x-y axis in order to display the similarity or difference between the two channels. A mono signal will produce a straight vertical line while signals with a wider stereo image will produce more horizontal shapes. A Vectorscope can be used to monitor the stereo width of a signal while mixing or mastering. It can also help to highlight potential issues with phase cancellation.


The following view modes are available in the stereo vectorscope:

- > Polar Sample
- > Polar Level
- > Lissajous

Sound Field Modes


Polar Sample

The Polar Sample Vectorscope plots dots per sample, but uses a polar coordinate display that is more useful in highlighting the stereo image of the incoming signal. Patterns that appear within the 45-degree safe lines represent in phase signals while patterns outside these lines represent out of phase audio. The history of the Polar Sample Vectorscope also fades out slowly. The infinite history is shown as the faintest shade of grey while the last few seconds are displayed as slowly fading data points. You can reset the display by clicking on the meter.




Polar Level

The stereo energy of a recording is clearly represented by the Polar Level Vectorscope which plots rays on a polar coordinate display that represent sample averages. The length of the rays represents amplitude while the angle of the rays represents their position in the stereo image. Rays within the 45-degree safe lines represent in phase audio while anything beyond these lines represents audio that is out of phase. History is represented on the Polar Level Vectorscope with the shrinking of the plotted rays slowly over time. The rays shrink towards the center of the vectorscope leaving the outer portion of the display for real-time analysis.



Lissajous

Like the Polar Sample vectorscope, the Lissajous Vectorscope plots per sample dots on a traditional oscilloscope display. Typically, stereo recordings produce a random pattern on a Lissajous Vectorscope that is taller than it is wide. Vertical patterns mean left and right channels are similar (approaching mono, which is a vertical line). Horizontal patterns mean the two channels are very different, which could result in mono compatibility problems.



The history of the Lissajous Vectorscope fades out slowly. The history is shown as the faintest shade of grey while the last few seconds are displayed as slowly fading data points. You can reset the display by clicking on the meter.

Clipping

The Vectorscope will draw any clipped samples in red.

Balance Meter

The horizontal bar meter below the stereo vectorscope display indicates the averaged stereo location of the input signal.


Correlation Meter

The vertical bar meter to the right of the stereo vectorscope display indicates the amount similarity (or correlation) between the left and right channels. When two signals are exactly the same (in phase) a reading of +1 would register on the correlation meter. When two signals are perfectly out of phase and thus completely different a reading of -1 would register on the correlation meter.

A Correlation Meter is used in stereo to ensure that the left and right signals will sum to mono without any cancellation of frequencies. If two signals are perfectly out of phase, then summing them would result in no audible audio. Typically, mixed audio will have values between 0 and +1 depending on the width of the stereo signal. Values that dip briefly below zero do not necessarily represent serious problems with your audio, but prolonged negative readings indicate issues with mono compatibility.

Surround Scope

The Surround Scope is a stylized display of the amplitude of surround channels. This display stresses the spatial relationship of the channels while still illustrating the level of each channel. The Surround Scope monitors the phase relationship between neighboring audio channels and displays an alert when there is a negative correlation or phase cancellation taking place.



Surround Amplitude

The Surround Amplitude Meter plots rays within a 360 degree readout with markers designating the various surround channels.

Surround Balance indicators

The Surround Balance Indicator displays a tracking dot in different locations on the 360 degree readout. The location of the dot represents the summed surround location of all channels.

Surround Correlation Alerts


Correlation Alerts which bring your attention to any potential issues of phase between neighboring channels. The cells bordering the 360 degree plot of the Surround Scope each represent a given channel relationship. Only prominent signals that are significantly out of phase will trigger the alerts.

Surround Meter Scale

The rings within the meter represent precise RMS signal levels of each of your channels. Signals below -60dB RMS will not register as vectors on the Surround Meter.

Options

To access the meter specific options, click the gear button in the upper left hand corner of the Sound Field meter panel.



The Sound Field options tab offers the following options:

METER TYPE

Selects between stereo or surround meter modes.

VECTORSCOPE MODE

Selects the stereo vectorscope meter type. This can also be set by clicking the corresponding buttons in the Sound Field meter panel when Stereo Vectorscope is selected.

VECTORSCOPE DETECTION METHOD

When in Polar Level mode, this determines how the sample averages are detected. Selects between Peak, RMS, and Envelope. Envelope mode can be most useful when analyzing amplitude as it detects even levels across all frequencies.

Layouts

Overview

The Layouts window offers the ability to save the current meter panel layout and the associated meter specific option states to a preset file. The Layouts preset manager can be opened by clicking on the Layout preset name display bar in the header of the Insight 2 plugin window.




The previous and next buttons to the right of the main layout name display bar can be used to quickly cycle through the layout preset list without opening the Layout preset manager window.



Layout Preset Manager

The following controls and functions are available in the Layout preset manager window:



- > **SHOW AT STARTUP:** When checked, the Layout preset manager window will automatically open every time Insight 2 is launched.
- > **LAYOUT PRESET SELECTOR LIST:** Displays a list of available layout presets and layout preset folders.
 - > **DEFAULT SETTINGS:** Returns the meter panel layout configuration and meter specific options to their factory default values.
 - > **WORKING SETTINGS:** Returns the meter panel layout configuration and meter specific options to their last modified values. This is useful for returning to an unsaved layout state after selecting a layout preset from the list.
 - > **LAYOUT PRESET FOLDERS:** Layout preset folders are displayed as they appear in the Presets directory on disk. Double-click on a folder name to rename it.
 - > **LAYOUT PRESETS:** Layout presets are displayed in the main list area of the layout preset manager. Single-click on a layout preset to load it. Double-click on a layout preset name to rename it.
- > **LAYOUT PRESET COMMENTS:** The area below the main layout preset selector list displays comment text associated with the currently selected layout preset. To edit the comment text, single-click on the comment text to open an inline edit box. Modify the text and use the return/enter key to save the changes and exit the inline edit box.
- > **LAYOUT PRESET FOOTER CONTROLS** The following controls are available in the footer of the Layout preset manager:




- > **ADD PRESET:** Creates a new layout preset from the current configuration.
- > **ADD FOLDER:** Creates a new layout preset folder.
- > **UPDATE PRESET:** Saves changes made to currently selected layout preset. Only available when selected preset has unsaved changes.
- > **CLOSE:** Closes the Layout preset manager window

Global Options

Overview

The global options window includes the following sections: **general**, **loudness**, **updates**, and **authorization**. These options save to a configuration file, which means that modifications to the factory default values will persist in new instantiations of Insight 2.



The buttons along the bottom of the Global Options window include the following functionality:

- > **Reset:** Resets all options to their factory default settings.
- > **Cancel:** Discards changes made since last opening the global options window and closes the window.
- > **Ok:** Saves changes and closes the global options window.

General

- > **Show tooltips:** Enables/disables the display of tooltip text.
- > **Send anonymous usage data:** Enables sending of anonymous usage data to iZotope to help improve Insight 2.

Loudness

- > **Enable automation data:** When checked, Insight 2 will broadcast loudness overflow and integrated loudness automation data to the DAW/NLE. Enable track automation in the DAW/NLE to write the loudness data to two automation envelopes.
 - > **Loudness overflow:** When the integrated loudness target has been exceeded, this will broadcast a value of "True", or "1". When the integrated loudness level is below the target, this will broadcast a value of "False" or "0".
 - > **Integrated loudness:** Broadcasts the integrated loudness measurement value. When this value has exceeded the loudness target, the automation events will be broadcast and written more often. When integrated loudness falls below the loudness target value, the automation events will be broadcast and written less often.
- > **Export Loudness CSV:** Saves a .csv file with loudness history values captured over the course of the current calculation. The .csv file includes four main pieces of information: **Timestamp:** h:m:s.ms, **Integrated Loudness**, **Short-term Loudness**, **Momentary Loudness**. The loudness measurements written to the .csv file are only written as absolute loudness values, even if Relative scale is selected in the Loudness meter options. The integrated loudness trace will not reflect dialogue-gated measurements, even if dialogue gate is selected in the targets control panel in the Loudness meter.

▲ EXAMPLE OF LOUDNESS HISTORY CSV EXPORT
h:m:s.ms,Integrated [LKFS],Short-term [LKFS],Momentary [LKFS],
00:00:0.5-16.3116,-33.7392,-13.5834,
00:00:1.0-15.0203,-22.6982,-12.3178,

LEARN MORE ABOUT LOUDNESS METERING

- > Learn more about the Loudness History meter in the [History](#) chapter.
- > Learn more about the Loudness meter in the [Loudness](#) chapter.

Updates

- > **Download Product Portal:** To stay up to date with new versions of Insight 2, download the iZotope Product Portal application.
- > **Check for Updates:** Manually check for available updates. Clicking this button will open the Product Portal application to check for updates.
- > **Download Update:** If an update is available, a small green dot will appear. Clicking the Download Update button in the Insight options window will open the Product Portal application and display the Updates page.

Authorization

This section displays information about the current authorization state of the Insight 2 plug-in.

- > **Current Authorization Status Text:** Displays the current Insight 2 authorization state.
- > **Authorize:** Opens the iZotope Authorization wizard.
- > **Remove Authorization:** Removes the current authorization.

LEARN MORE ABOUT AUTHORIZATION

- > Learn more about authorizing Insight 2 in the [Authorization](#) chapter.
- > Learn more about using the iZotope Product Portal application to install, authorize or update iZotope products: [About Product Portal](#)
- > Visit the iZotope Authorization Support page for more information on authorization: [iZotope Authorization Support](#)

Relay

Overview


Relay can send metering data to and receive information from select Inter Plug-in Communication (IPC) compatible iZotope plug-ins, including: Insight 2, Tonal Balance Control, Neutron 2, Neutron 2 EQ plug-in, and Neutron 2 Visual Mixer.

Relay and Insight 2

Relay can send metering data to the Spectrogram and Intelligibility meters in Insight 2.


Relay in the Spectrogram

Up to eight Relay instances can be displayed at once in the Spectrogram meter panel in Insight 2.




Relay in the Intelligibility Meter

Relay instances can be selected as a Source in the Intelligibility meter panel in Insight 2.



Relay and Tonal Balance Control

Relay can be selected as a source in the Tonal Balance Control plug-in.



Relay and Neutron 2 Masking Meter

Relay can be selected as a source in the Masking Meter included in Neutron 2 (EQ module) and the Neutron 2 EQ component plug-in.




Relay and Neutron 2 Visual Mixer

Relay controls can be remotely modified in the Neutron 2 Visual Mixer. Moving a Relay node up or down in the Visual Mixer will adjust the gain slider in the remote instance. Moving a Relay node left or right in the Visual Mixer will adjust the pan control in the remote instance (stereo Relay instances only). Dragging Relay node handles in the Visual mixer will adjust the width parameter in the remote instance (stereo Relay instances only).



Relay and Nectar 3

Relay can be used as an Unmask source in Nectar 3 Vocal Assistant. When masking is detected between the Nectar 3 instance and the Relay instance, an EQ curve will be applied to the Relay instance in order to reduce masking of the vocal track. When the EQ curve is active, Relay will display the track name it is unmasking. The EQ curve can be disabled by clicking on the "Unmasking" status button in the Relay interface.



■ Authorization

Overview

The iZotope Authorization window will appear the first time you open **Insight 2** in your DAW or NLE.

The Authorization window allows you to:

- › **TRIAL:** Start or continue a 10 day Trial period prior to purchasing.
- › **DEMO:** Evaluate the product with Demo limitations.
- › **AUTHORIZE:** Authorize the product with a serial number.

Trial & Demo Modes

A 10 day trial period will start the first time **Insight 2** is opened in your DAW or NLE. When the 10 day trial period has expired, **Insight 2** will operate in demo mode until authorized with a valid serial number.

Trial Mode

Upon opening **Insight 2** in your DAW or NLE, the authorization wizard window will appear and display the number of days remaining in your trial period.

Clicking "Continue" will dismiss the Authorization window and allow you to continue evaluating **Insight 2** in trial mode with full functionality.

Demo Mode

When the 10 day Trial period has expired, enter a valid serial number to authorize the product or use **Insight 2** in Demo mode. All meters are disabled when **Insight 2** is run in Demo mode.

Authorizing Insight

We offer three methods for authorizing **Insight 2**:

1. **Online Authorization:** Use this method to authorize **Insight 2** on a machine that is connected to the internet.
2. **Offline Authorization:** Use this method to authorize **Insight 2** on a machine that is not connected to the internet.
3. **iLok Authorization:** Use this method to authorize **Insight 2** using an iLok.

More Information

For information on authorization, please visit the iZotope website: <https://www.izotope.com/authorization>

For additional help with authorizing **Insight 2**:

- › Check out the Customer Care pages on the iZotope website: <http://www.izotope.com/support>
- › Contact our Customer Care department at support@izotope.com

More information on iZotope's Customer Care department and policies can be found in the [Customer Care](#) chapter.

Customer Care

iZotope Customer Care Policy

iZotope is happy to provide professional technical Customer Care to all registered users absolutely free of charge. [Contact iZotope Customer Care](#)

We also offer valuable pre-sales technical Customer Care to customers who may be interested in purchasing an iZotope product. Before contacting iZotope Customer Care, you can search our [Product Knowledgebase](#) to see if the solution to your problem has already been published.

How long does iZotope provide customer support for purchased products?

You can email us with any question for 12 months after you buy any iZotope product. Past 12 months, we'll still help you with your account and authorization but will not provide technical support for in-depth product questions. If you need more detailed help on how to use the product, please check out our FAQs and Tutorials.

How long does iZotope support its products?

Although we can't guarantee it, we do our best to keep our products up to date with the operating systems and plug-in hosts that we support. Sometimes, other companies make changes that we're not able to support, but we actively work with other companies to avoid these sorts of compatibility problems. We also do our best to address bug fixes within the product itself to ensure our products operate in accordance with our specifications.

We will provide software updates for 12 months from product release. After 12 months, no software updates will be provided.

For details on what operating systems and plug-in host software are officially supported for a product, please check that product's specs page.

Contacting iZotope Customer Care

For additional help with Insight 2:

- Check out the Customer Care pages on our web site at www.izotope.com/support
- Contact our Customer Care department at support@izotope.com

iZotope's highly trained Customer Care team is committed to responding to all requests within one (1) business day and frequently respond faster. Please try to explain your problem with as much detail and clarity as possible. This will ensure our ability to solve your problem accurately, the first time around. Please include all system specs and the build/version of Insight 2 that you are using.

Once your Customer Care request is submitted, you will receive a confirmation email from iZotope Customer Care. If you do not receive this email within a few minutes, please check your spam folder and make sure our responses are not getting blocked. To prevent this from happening please add support@izotope.com to your list of allowed email addresses.

International Distribution

Customer Care is also available from our international distributors worldwide for any customers who purchased their iZotope products through a certified iZotope distributor.

Check with your local distributor for availability. If you would like help locating your local distributor please contact iZotope Customer Care.

Thanks for using Insight 2!

- The iZotope Team
-

END USER LICENSE AGREEMENT

READ CAREFULLY THE TERMS AND CONDITIONS OF THIS AGREEMENT ("AGREEMENT") BEFORE YOU CLICK ON THE "ACCEPT" BUTTON OR OTHERWISE USE THE PRODUCT. CLICKING ON THE "ACCEPT" BUTTON OR OTHERWISE DOWNLOADING, INSTALLING AND/OR USING THE LICENSED SOFTWARE OR ANY TECHNOLOGY, IDEA, DATA AND DATABASES, ALGORITHM OR INFORMATION CONTAINED THEREIN OR PROVIDED THEREWITH (COLLECTIVELY, THE "SOFTWARE"), ESTABLISHES A BINDING AGREEMENT BETWEEN YOU AS THE PERSON LICENSING THE SOFTWARE, EITHER ON BEHALF OF YOURSELF OR ANY THIRD PARTY ENTITY ("YOU" OR "LICENSEE") AND IZOTOPE, INC. ("IZOTOPE"). YOU (WHETHER AN INDIVIDUAL OR FORMAL LEGAL ENTITY) (HEREINAFTER REFERRED TO AS "YOU"), AGREE TO BE BOUND BY THE TERMS AND CONDITIONS OF THIS AGREEMENT WITH RESPECT TO YOUR USE OF THE SOFTWARE.

BY INSTALLING AND/OR BY USING THE SOFTWARE, YOU REPRESENT AND WARRANT THAT YOU HAVE THE LEGAL CAPACITY AND AUTHORITY TO ENTER INTO A BINDING AGREEMENT TO ADHERE TO THE TERMS AND CONDITIONS SET FORTH HEREIN, AND THAT THE SOFTWARE WILL BE USED ONLY IN ACCORDANCE WITH THESE TERMS AND CONDITIONS AND WITH ALL APPLICABLE LAWS. IF AN INDIVIDUAL IS REGISTERING OR USING THE SOFTWARE ON BEHALF OF AN ENTITY OR ORGANIZATION, THAT INDIVIDUAL WARRANTS, REPRESENTS, AND COVENANTS TO IZOTOPE THAT SUCH INDIVIDUAL IS DULY AUTHORIZED TO AGREE TO THESE TERMS AND CONDITIONS ON BEHALF OF THE ORGANIZATION AND TO BIND THE ORGANIZATION TO THEM.

LICENSE. Subject to all the terms and conditions of this Agreement, IZotope hereby grants to Licensee a license to use the Software accompanying this Agreement, as well as any presets and documentation provided, whether in printed, "online" or electronic form, either on a stand-alone computer or on a network, on any one computer at any one time. If more than one user will be using the Software at any one time, you must obtain from IZotope additional license(s) for each additional concurrent user of the Software. The Software is "in use" on a computer when loaded into memory (RAM). You may make one copy of the Software solely for backup or archival purposes if all copyright and other notices are reproduced on that copy, or you may copy the Software to a single hard disk provided you keep the original solely for backup or archival purposes. If the Software is an upgrade, you must have a license for the Software from which it is upgraded. If you receive the Software in more than one media, that does not affect the number of licenses you are receiving or any other term of this Agreement.

OWNERSHIP. The copyrights, patents, trade secrets, trademarks, and all other intellectual property rights in the Software and documentation (including any images, photographs, animations, video, audio, music and text incorporated in them) are owned by IZotope or its suppliers and are protected by the copyright, patent and other laws of the United States and other countries and by international treaty provisions. IZotope retains all rights not expressly granted in this Agreement. You shall not remove any product identification, trademark, copyright or other notices contained in or on the Software.

OTHER RESTRICTIONS. You may not modify, adapt, decompile, disassemble or otherwise reverse engineer the Software, except to the extent this restriction is expressly prohibited by applicable law, nor may you create derivative works based upon the Software, or to permit third parties to do so. You may not loan, rent, lease, or license the Software, or use the Software as a service bureau, as an application service provider, to perform consulting or training services for a third party or in any commercial time share arrangement, but you may permanently transfer your rights under this Agreement provided you transfer this Agreement, the Software, and all accompanying printed materials and retain no copies, and the recipient agrees to the terms of this Agreement. Any such transfer must include the most recent update and all prior versions.

LIMITED WARRANTY. IZotope warrants that, for a period of thirty (30) days from the date the Software is made available to you for download, the Software will substantially conform to the applicable user documentation provided with the Software. Any implied warranties which may exist despite the disclaimer herein will be limited to thirty (30) days ("Warranty Period"). This limited warranty is void if you buy from an unauthorized reseller, you violate the terms of this Agreement, or if the failure of the Software is due to accident, abuse or misapplication. Some states/jurisdictions do not allow limitations on duration of an implied warranty, so this limitation may not apply to you.

YOUR REMEDIES. IZotope's sole obligation and your exclusive remedy for any breach of warranty will be, at IZotope's sole option, either the return of the purchase price you paid or the repair or replacement of the Software, media and documentation, provided you in all instances return the Software, together with all media and documentation and a copy of your receipt, to the location where you obtained it during the Warranty Period. Outside the United States, neither these remedies nor any support services are available without proof of purchase from an authorized non-U.S. source.

SUPPORT. Subject to the limited warranty stated above, and further subject to you not being in violation of any term of this Agreement, IZotope will provide email support for the Software to the original purchaser, for a period of 12 months from the original purchase date.

REGISTRATION INFORMATION. When you activate the Software, IZotope may collect your name and email address and other contact information you choose to provide. IZotope may use this information to contact you regarding upgrades and new products. IZotope does not collect or retain any financial information (such as credit card information).

USAGE INFORMATION. When you activate and/or use the Software, IZotope may collect certain information about your computer and your interaction with the Software via the internet ("Usage Information"). Usage Information is information on how you interact with the Software, and is then utilized by IZotope for statistical analysis for improving the Software, and to provide you with a more relevant user experience. No direct personal information or audio files/samples are collected as part of this Usage Information. Usage Information is generally collected in the aggregate form, without identifying any user individually, although IP addresses, computer and session ids in relation to purchases and downloads/installations of the Software may be tracked as part of IZotope's customer order review, statistical analysis, and fraud and piracy prevention efforts. This Usage Information may be sent to an IZotope web or third-party cloud server for storage or further processing by IZotope and/or its partners, subsidiaries or affiliates, including, but not limited to, Google Analytics. The Software includes an opt-out provision if you do not wish to provide IZotope with such Usage Information.

DISCLAIMER. THE SOFTWARE IS PROVIDED "AS IS" TO THE MAXIMUM EXTENT PERMITTED BY APPLICABLE LAW, EXCEPT FOR THE EXPRESS WARRANTY SET FORTH HEREIN. IZOTOPE DISCLAIMS ALL OTHER WARRANTIES, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE. IZOTOPE DOES NOT WARRANT THAT THE SOFTWARE WILL MEET YOUR REQUIREMENTS OR THAT THE SOFTWARE WILL OPERATE UNINTERRUPTED OR ERROR-FREE. THE WARRANTY AND REMEDIES SET FORTH HEREIN ARE EXCLUSIVE AND IN LIEU OF ALL OTHERS, ORAL OR WRITTEN, EXPRESS OR IMPLIED. No dealer, distributor, agent or employee of IZotope is authorized to change or add to the warranty and remedies set forth herein. Any other software furnished with or accompanying the Software is not warranted by IZotope.

LIMITATION OF LIABILITY. TO THE MAXIMUM EXTENT PERMITTED BY APPLICABLE LAW, IN NO EVENT WILL IZOTOPE BE LIABLE FOR ANY AMOUNTS EXCEEDING THE AMOUNTS RECEIVED FROM YOU FOR YOUR LICENSE OF THE SOFTWARE, REGARDLESS OF THE FORM OF ACTION, AND WHETHER ARISING OUT OF THE USE OF OR INABILITY TO USE THE SOFTWARE (INCLUDING, WITHOUT LIMITATION, DAMAGES OR COSTS FOR LOSS OF PROFITS, BUSINESS, GOODWILL, DATA OR OTHER ASSETS, OR COMPUTER PROGRAMS) EVEN IF IZOTOPE HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES. Some jurisdictions do not allow exclusion or limitation of liability for consequential or incidental damages, so this limitation may not apply to you.

TERMINATION. The Agreement will terminate automatically if you fail to comply with any of its terms. On termination, you must immediately cease using and destroy all copies of the Software.

LICENSES TO U.S. GOVERNMENT. This paragraph applies to all acquisitions of the Software by or for the federal government, or by any prime contractor or subcontractor (at any tier) under any contract, grant, cooperative agreement or other activity with the United States government (collectively, the "Government"). By clicking "ACCEPT", you are agreeing on behalf of the Government that the Software and any documentation related thereto are respectively "commercial computer software" and "commercial computer software documentation" within the meaning of the acquisition regulation(s) applicable to this procurement. These terms and conditions alone will govern the Government's use of the Software and will supersede any conflicting contractual terms or conditions. If the license granted by these terms and conditions fails to meet the Government's needs or is inconsistent in any respect with Federal law, the Government must return the Software unused to IZotope. Contractor/Manufacturer is IZotope, Inc., 60 Hampshire Street, Cambridge, MA 02139.

GENERAL. The export of the Software from the United States and re-export from any other country is governed by the U.S. Department of Commerce under the export control laws and regulations of the United States and by any applicable law of such other country, and the Software may not be exported or re-exported in violation of any such laws or regulations. This Agreement is the complete and exclusive statement of the agreement between you and IZotope and supersedes any proposal or prior agreement, oral or written, and any other communications relating to the subject matter of this Agreement. This Agreement will be governed by and interpreted under the laws of the Commonwealth of Massachusetts, United States of America, without regard to conflicts of law provisions. The application of the United Nations Convention of Contracts for the International Sale of Goods is expressly excluded. This Agreement is in the English language only, which language will be controlling in all respects, and all versions of this Agreement in any other language will be for accommodation only.

IN ADDITION, ANY SUCH LEGAL PROCEEDING SHALL NOT BE HEARD BEFORE A JURY. EACH PARTY GIVES UP ANY RIGHT TO A JURY TRIAL. To the extent permitted by law, you agree that you will not bring any class action lawsuit against IZotope or be a representative plaintiff or plaintiff class member in any such lawsuit.

Should you have any questions about this Agreement or IZotope's software use policies, or if you desire to contact IZotope for any other reason, in the U.S., please email sales@izotope.com; outside the U.S., please contact the IZotope representative or affiliate serving your country or, if you are unsure whom to contact, IZotope at the above location. Please indicate that you understand and accept these terms by clicking the "Accept" option. If you do not accept these terms, installation will terminate.

License Information

Anti-Grain Geometry

Version 2.4

Copyright © 2002-2005 Maxim Shemanarev (McSeem).

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
3. The name of the author may not be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE AUTHOR "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

Better Enums

Version 0.11.1

Copyright © 2012-2016, Anton Bachin. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

Dolby Dialogue Intelligence Technology

Created under license from Dolby Laboratories Licensing Corporation. Use of this Software does not convey a license nor imply a right under any patent, or any other industrial or intellectual property right of Dolby Laboratories.

For further information regarding patents, see the "Patents" and "Patent Applications" sections here: <https://www.dolby.com/us/en/technologies/speech-gating-reference-code/agreement.html>

fmt

Version 4.0.0

Copyright © 2012 - 2016, Victor Zverovich

All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

FreeType

FreeType is licensed under the FreeType Project LICENSE.

Portions of this software are copyright © 1996-2002, 2006 The FreeType Project (www.freetype.org). All rights reserved.

gsl

Copyright © 2015 Microsoft Corporation. All rights reserved.

This code is licensed under the MIT License (MIT).

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

IcoMoon

IcoMoon-Free licensed under: [CC BY 4.0](#)

JsonCpp

Version 1.2.1

Copyright © 2007-2010 Baptiste Lepilleur and The JsonCpp Authors

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

LibXML2

Version 2.7.8

Except where otherwise noted in the source code (e.g. the files hash.c, list.c and the trio files, which are covered by a similar licence but with different Copyright notices) all the files are:

Copyright © 1998-2003 Daniel Veillard. All Rights Reserved.

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE DANIEL VEILLARD BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Except as contained in this notice, the name of Daniel Veillard shall not be used in advertising or otherwise to promote the sale, use or other dealings in this Software without prior written authorization from him.

Material Docs Theme

Copyright © 2016 Digitalcraftsman digitalcraftsman@protonmail.com

Copyright © 2016 Martin Donath martin.donath@squidfunk.com

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

nanomsg

Version 0.5-beta

Copyright © 2012-2013 Martin Sustrik. All rights reserved.

Copyright © 2013 GoPivotal, Inc. All rights reserved.

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

"nanomsg" is a trademark of Martin Sustrik

readerwriterqueue

Copyright © 2013-2015, Cameron Desrochers
All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT HOLDER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

Skia

Copyright © 2011 Google Inc. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- Neither the name of Google Inc. nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

TagLib

Version 1.9.1

Copyright © 1995-2015 Scott Wheeler, Lukas Lalinsky, Ismael Orenstein, Allan Sandfeld Jensen, Teemu Tervo, Mathias Panzenböck, and Tsuda Kageyu.

Distributed under the [Mozilla Public License v1.1 \(MPLv1.1\)](#).

TinyXML

Copyright © 2000-2002 Lee Thomason (www.grinninglizard.com)

This software is provided 'as-is', without any express or implied warranty. In no event will the authors be held liable for any damages arising from the use of this software.

Permission is granted to anyone to use this software for any purpose, including commercial applications, and to alter it and redistribute it freely, subject to the following restrictions:

- The origin of this software must not be misrepresented; you must not claim that you wrote the original software. If you use this software in a product, an acknowledgment in the product documentation would be appreciated but is not required.
- Altered source versions must be plainly marked as such, and must not be misrepresented as being the original software.
- This notice may not be removed or altered from any source distribution.

Tipue Search

Copyright © 2017 Tipue

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

vectorize

Copyright © 2012 Aaron Wishnick. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- Neither the name of the nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

Yoga

Version 1.9.0

MIT License

Copyright © 2014-present, Facebook, Inc.

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

ZeroMQ

Copyright © 2007-2015 iMatix Corporation
Copyright © 2009-2011 250bpm s.r.o.
Copyright © 2010-2011 Miru Limited
Copyright © 2011 VMware, Inc.
Copyright © 2012 Spotify AB
Copyright © 2013 Ericsson AB
Copyright © 2014 AppDynamics Inc.

Distributed under the [GNU Lesser General Public License v3 \(LGPLv3\)](#).

Full text of the license is available here: <https://www.gnu.org/licenses/lgpl-3.0.txt>

To receive a copy of the source code for the ZeroMQ library distributed with this product under the under the terms of the LGPLv3 please contact devsupport@zotote.com.

zlib

Copyright © 1995-2004 Jean-loup Gailly and Mark Adler.

This software is provided 'as-is', without any express or implied warranty. In no event will the authors be held liable for any damages arising from the use of this software.

Permission is granted to anyone to use this software for any purpose, including commercial applications, and to alter it and redistribute it freely, subject to the following restrictions:

1. The origin of this software must not be misrepresented; you must not claim that you wrote the original software. If you use this software in a product, an acknowledgment in the product documentation would be appreciated but is not required.
2. Altered source versions must be plainly marked as such, and must not be misrepresented as being the original software.
3. This notice may not be removed or altered from any source distribution.

Jean-loup Gailly jloup@gzip.org

Mark Adler madler@alumni.caltech.edu
